

PREPARING/KASHERING THE PESACH KITCHEN

Rabbi Moshe Heinemann, STAR-K Rabbinic Administrator

See also Cleaning/Kashering Checklist on page 34.

As the Yom Tov of Pesach nears, and the diligent balabusta begins to tackle the challenge of preparing the kitchen for Pesach, undoubtedly the light at the end of the tunnel is beginning to shine. Although moving into a separate Pesach home sounds very inviting, such luxuries are often not affordable and definitely not in the Pesach spirit. Among the basic mitzvos of the *chag* is the mitzvah of *tashbisu se'or mibateichem*, ridding one's home and possessions of chometz. However, if we are to use kitchen equipment, utensils, or articles that can be found in our kitchen year-round, it may be insufficient to just clean them thoroughly. One is forbidden to use these items unless they have been especially prepared for Pesach. This preparation process is known as *kashering*.

The Torah instructs us that the proper *kashering* method used to rid a vessel of chometz is dependent upon the original method of food preparation through which chometz was absorbed into the vessel.

When possible, it is preferable for a person knowledgeable in the laws of *kashering* to be present during the *kashering* process. *Kashering* must be finished before the latest time to burn the chometz (see page 39). If *kashering* was not done before this time, consult your *rav*. For *Kashering Safety Tips* from Hatzalah, go to star-k.org/passover.

Kashering Methods

Kashering methods can be broadly grouped into one of the following categories:

METHOD	DEFINITION
<i>Libun Gamur</i>	Heating metal to a glow
<i>Libun Kal</i>	Heating metal above the temperature that will burn paper
<i>Hagola</i>	Purging through immersion in hot water
<i>Iruy Roschin</i>	Purging through a hot water pour
<i>Miluy V'Iruy</i>	Soaking

It is important to note that where *libun kal* helps, certainly *libun gamur* is good; where *hagola* helps, surely *libun kal* is good; and where *iruy* helps, certainly *hagola* and *libun* help.

We will now discuss how to properly *kasher* or prepare kitchen appliances and cookware for Pesach using one of the above-described *kashering* methods.

Kashering the Oven

No part of the stove can be considered *kashered* for Pesach unless it is completely clean and free from any baked-on food or grease. This includes the oven, cooktop, and broiler.

Conventional Oven

In a conventional oven, whether gas or electric, an oven cleaner may be necessary to remove baked-on grease. Be sure to check hidden areas including corners, door edges, the area behind the flame burners, and the grooves of the rack shelves. If a caustic type of oven cleaner (such as Easy-Off) was used to clean the oven, and some stubborn spots remained after a second application with similar results, the remaining spots may be disregarded. Once the oven and racks have been cleaned, they may be *kashered* by *libun kal*. The requirement of *libun kal* is satisfied by turning the oven to broil, or the highest setting for 40 minutes. In a gas oven, the broil setting will allow the flame to burn continuously. In a conventional electric oven, the highest setting (550°F) *kashers* the oven. Only *libun kal* is required for the oven racks, since it is usual to cook food in a pan and not directly on the racks themselves.

Self-Cleaning Oven

In a self-cleaning oven, before using the self-clean cycle, one should clean the inside face of the oven door as well as the opposing outer rim of the oven outside the gasket, since these areas are not necessarily cleaned during the cycle. One should ensure that the gasket itself is clean on the area outside the oven seal. (NOTE: The gasket is sensitive to abrasion.) The self-cleaning cycle will then clean and *kasher* the oven simultaneously.

Caution: There is a potential risk of fire during the self-cleaning process, especially if there is a build-up of grease on the bottom of the oven. It is recommended that one apply Easy Off, made especially for self-clean ovens, to lift and remove the grease. The oven should not be left unattended while in the self-cleaning mode.

Most oven manufacturers instruct the consumer to remove the oven racks before self-cleaning so they will not discolor. However, one may self-clean the oven with the racks inside even though they might discolor. After the self-clean cycle, one should use a little oil on the side of the racks to easily slide them in and out of the oven. There are some manufacturers that also require removal of the racks before the self-clean cycle can start. In this case, one should take the racks out, clean them very well, and then put them in the oven at the highest temperature (usually 550°F) for 40 minutes. This procedure *kashers* the racks.

Some ovens come with a convection feature. This feature allows for more uniform heat distribution by using a fan to circulate the heat. If the convection oven has the self-cleaning feature it will be sufficient to also *kasher* the fan using

the self-clean *kashering* method previously mentioned. If there is no self-cleaning feature, the entire oven including the fan while it is circulating, must be sprayed with a caustic cleaner and cleaned well. The oven should then be *kashered* by turning it on to the 550°F setting for forty minutes.

Please note that many ovens today have 'Aqualift' or 'Steam Clean' instead of a conventional self-cleaning feature. Neither 'Aqualift' nor 'Steam Clean' get hot enough to *kasher* the oven. Instead, use the Conventional Oven *kashering* method as described above.

Oven Hoods and Exhaust Fans

Hoods and exhaust fan filters should be cleaned and free of any food residue.

Broiler and Broiler Pan

The broiler pan cannot be *kashered* by merely turning on the gas or electricity. Since food is broiled or roasted directly on the pan, the pan must be heated to a glow in order to be used during Pesach. This can be done by the use of a blowtorch (but only by qualified and experienced individuals). It is recommended they do this in a darkened room to more easily observe when the metal is glowing. An alternative method is to replace the broiler pan.

The empty broiler cavity must then be *kashered* by cleaning and setting it to Broil for 40 minutes. If one does not intend to use the broiler, one may still use the oven even without *kashering* the broiler, provided that the broiler has been thoroughly cleaned.

Other inserts such as **griddles**, which come into direct contact with food, are treated the same as broiler pans. Therefore, they would also require application of direct heat until the surface glows red. Otherwise, the insert should be cleaned and not used during Pesach.

Warming Drawers

Warming drawers cannot be *kashered* because the heat setting does not reach high enough to constitute *libun*. The warming drawer should be cleaned, sealed, and not used during Pesach.

Microwave Ovens

When microwaves are used, they do not necessarily absorb chometz. The microwave should be tested to see if the walls become hot during use. To do this, one should cook an open potato in the microwave until it has been steaming for a few minutes. Immediately after the potato has been cooked, one should place his hand on the ceiling of the microwave to see if it has become too hot to touch. If one cannot hold his hand there for 15 seconds, we assume that the microwave has absorbed chometz. If this is the case, the microwave should be cleaned and sealed for Pesach. If it has not absorbed chometz (i.e., one can hold his hand there for 15 seconds), the microwave itself needs only to be cleaned well.

It is recommended that one wait 24 hours before using the microwave on Pesach. The turntable should be replaced because it has come into contact with hot food and would not pass the hand test. One may replace the turntable with a ¼" Styrofoam board.

Microwave ovens that have a convection or browning feature must be *kashered* using the convection and/or browning mode. The *kashering* method used would be *libun kal*. The convection microwave should first be cleaned well. If the fan area cannot be properly cleaned, it should be sprayed with a caustic cleaner (e.g., Easy Off) while the fan is on, and rinsed off before *kashering*. One should then test the convection microwave to see if it reaches the required heat for *libun kal* by putting it on its highest setting for 40 minutes. A piece of paper should then be held against the interior wall to see if it gets singed.¹ If the paper is singed, the convection microwave has been heated sufficiently for *libun kal* and can be considered *kashered*. Many models fail the test because their settings do not allow the microwave to become hot enough for *kashering*. If this is the case, the microwave should be cleaned, sealed, and not used during Pesach.

Kashering The Cooktop

Gas Cooktop

On a conventional gas range, the cast iron or metal grates upon which the pots rest may be inserted into the oven after they have been thoroughly cleaned. The grates can then be *kashered* simultaneously with the oven. (If *kashering* with a self-clean cycle, the grates do not need to be cleaned first. However, it is advisable to check with the manufacturer as to whether the grates would be able to withstand a self-clean cycle. Some grates have rubber feet that may be damaged by the heat of the oven or may damage the oven itself.) **Note:** The self-cleaning cycle may remove the paint finish if the grate is not manufactured to withstand the self-clean cycle.

The rest of the range (not glasstop) should be cleaned and covered with a double layer of heavy duty aluminum foil, which should remain on the range throughout Pesach.

Please Note: Extreme caution should be taken not to cover over the vent so as to allow the oven heat to escape. The drip pans should be thoroughly cleaned and need not be *kashered*. The burners and caps do not require *kashering* or covering but should be cleaned.

Electric Cooktop

In a conventional electric cooktop, one is required to clean the burners well and then turn them on to a high heat setting until they are glowing hot. (This

1. השיעור של קש נשרף עליו הוא מבחוח וכאן הוא מבפנים, אבל בתנורים שלנו א"א להבחין אם נשרף עליו מבחוח, מפני שיש לתנור שני כותלים וביניהם חומר המקיים את החום, וא"א להגיע לבחוח של כותל הפנימי. ונ"ל שכשפותחים את התנור וכנס אויר קר לתוך התנור, אז הכותל הפנימי מבפנים הוא יותר קר מכותל הפנימי מבחוח שמכוסה מכל הצדדים.

usually takes only several minutes.) The drip pans should be thoroughly cleaned and need not be *kashered*. The remaining cooktop areas should be cleaned and covered. The knobs with which the gas or electricity is turned on and off should be cleaned. No other process is necessary to *kasher* the knobs.

Please Note: All ovens ventilate hot steam during cooking. In the past, the hot steam was ventilated through the back of the oven. Today, many ranges no longer ventilate in this manner. The oven steam is ventilated through one of the rear cooktop burners. During oven cooking, if the rear vented burner is turned off and covered by a pot or kettle, the hot steam will condense on the burner and utensils. This could create hot *zei'a* (condensate) that can cause serious kashrus problems with the utensil if the food cooked in the oven is a meat product and the pot on the burner is dairy or *pareve*, or vice versa. Care should be exercised with the vented burner to keep it clear during oven cooking or baking.

Caution: When placing aluminum foil over the oven backsplash, be careful not to trap the heat coming from the oven vent between the foil and the backsplash; doing so may melt the backsplash if the oven vents through the back.

Sensi-Temp Burner

To *kasher* a Sensi-Temp burner for Pesach, remove the burner from the range top by lifting it up halfway to vertical and pulling it out. Clean it well and wait 24 hours. Once that time has elapsed, pour boiling water over the sensor, which is located in the middle of the burner. Insert the burner back into its socket by reversing the extraction steps. Turn the burner on to its maximum setting until it glows (about 2 minutes).

Electric Cooktop with Glass Surface

Kashering a glass-ceramic electric cooktop for Pesach use is a bit complex. To *kasher* the burner area, one should clean it well and turn on the elements until they glow. The burner area will then be considered Kosher for Passover. However, the remaining area that does not get hot is not *kashered*. The manufacturers do not suggest covering this area as one would a porcelain or stainless steel cooktop, as it may cause the glass to break. Real *kosherization* can be accomplished by holding a blowtorch over the glass until it is hot enough to singe a piece of newspaper upon contact with the glass. However, this may cause the glass to shatter and is not recommended.

As the area between the burners cannot practically be *kashered*, it would be wise to place a trivet on the open glass area so the pots can be transferred.

In order to use a large pot that extends beyond the designated cooking area, STAR-K recommends one of these solutions: (1) Use a cooktop mat specifically made for glass stovetops. (2) Place a metal disc approximately 1/8 of an inch thick onto the burner area in order to raise the Passover pots above the rest of the glass surface. (CAUTION: This disc should not extend beyond the designated cooking

area.) Or, (3) Use a stovetop heat diffuser made specifically for glass stovetops. Each of the above suggestions will help alleviate the concern of a pot boiling over, with the resulting trickle of hot liquid serving as a conduit from the Pesachdig pot to the non-Passover stovetop, posing a *halachic* concern.

NOTE: Caution should be taken to obtain devices that will not harm the surfaces. Cooking efficiency may be somewhat compromised when using these devices.

Gas Cooktop With a Glass Surface

For gas stovetops with a glass surface, one may *kasher* the grates by putting them into the oven with *libun kal* (550°F for 40 minutes). In most such models, the grates cover the entire top of the stove and there should be no problem adjusting pots on the stovetop. Food which falls through the grates and touches the glass surface should not be used.

For those models where the grates do not cover the entire cooktop surface it would be wise to place a trivet on the open glass area so that pots may be transferred. No food or pots may come into direct contact with the non-*kashered* glass surface.

Some gas cooktops have an electric warming area on the glass top. In order to *kasher* this area, it would have to become red hot when turned on. Many of these warming areas do not become hot enough for *kashering* and may not be used on Pesach.

Induction Cooktop

Before *kashering* an induction cooktop, it must be thoroughly cleaned and then left unused for at least 24 hours. The cooktop then requires *iruy roschin*. (Refer to instructions below for *kashering* a stainless steel sink by using *iruy roschin*.)

Note: Induction cooktops are not permitted to be used on Shabbos and Yom Tov.

Kashering Barbeque Grills

Note: *Kashering* a grill can be dangerous and should only be performed by competent individuals.

A grill cannot be *kashered* by simply turning on the gas or electricity. Since food is roasted directly on the grill, it must be heated to a glow in order to be used. This can be done by sandwiching the grates between the charcoal briquettes and setting them on fire. An alternative method is to replace the grates of the grill. The part of the grill cavity which is level with the grate must also be *kashered* by heating it to a glow. This is due to the likelihood of food having touched that area during barbecuing. The empty gas grill cavity (and the hood) must be *kashered* by cleaning, closing the hood, and setting it to the highest setting for 40 minutes. In the case of a regular grill, the cavity should be filled with charcoal briquettes which should be set on fire.

Other inserts such as griddles, which come into direct contact with food, are

treated the same as a grill and would, therefore, also require application of direct heat until the surface glows red. Otherwise, the insert should be cleaned and not used during Pesach. If the grill has side burners, they should be treated like cooktop grates, assuming no food has been placed directly on them. It is easier to determine that the metal has been brought to a glow in a darkened room.

Kashering Metal Utensils

Metal utensils (e.g., stainless steel/cast iron/aluminum serveware; silver/pewter *bechers*/Kiddush cups) that have been used for cooking, serving, eating, or washed with hot chometz may be *kashered*. This may be done by cleaning the utensils thoroughly and waiting 24 hours before immersing them, one by one, into a *Kosher l'Pesach* pot of water heated to a rolling boil. A rolling boil should be maintained while the vessel is immersed.

Note: Follow these steps with care! The metal utensil or vessel should be submerged into the boiling water for about 15 seconds. The utensils undergoing the *kashering* process may not touch one another. In other words, if a set of flatware is being *kashered* for Pesach, one cannot take all the knives, forks and spoons and put them into the boiling water together. Each of these items should be placed into the boiling water separately.

KASHERING TIP: Loosely tie the pieces of silverware to a string, leaving three inches between each piece, and immerse the string of silverware slowly, making sure the water keeps boiling.

The process is finalized by rinsing the *kashered* items in cold water. If tongs are used to grip the utensil, the utensil will have to be immersed a second time with the tongs in a different position so that the boiling water will touch the initially gripped area. Unlike *tevilas keilim*, the entire utensil does not have to be immersed in the boiling water at once; it may be immersed in parts.

A *non-Kosher l'Pesach* pot may also be used, *l'Halacha*, for the purpose of *kashering* if it is clean and has not been used for 24 hours. However, it is customary to make the pot *Kosher l'Pesach* before using it for *kashering*. This is accomplished by cleaning the pot, both inside and out, and leaving it dormant for 24 hours. The pot should then be completely filled with water and brought to a rolling boil. Using a pair of tongs, one should throw a hot stone or brick into a pot that has been heated on another burner. The hot rock will cause the water to bubble more furiously and run over the top ridge of the pot on all sides at one time. (One should use caution, as the hot water may spray in all directions.) The *kashering* process is finalized by rinsing the pot in cold water. The pot may now be refilled, brought to a boil, and used to *kasher* the chometz utensils. It is a *minhag* to re-*kasher* the pot after *kashering* if it is intended for Pesach use.

EXTRA BONUS: After this *kashering* process has taken place, the status of these newly *kashered* utensils may be changed from *milchig* to *fleishig* or vice versa, or *pareve*.

Kashering/Preparing Kitchen Sinks for Use on Pesach

Sinks are generally made from either stainless steel, granite composite, china, porcelain enamel, or man-made materials such as Corian.

Stainless Steel Sinks

Can be *kashered* using *iruy roschin*, as follows: Clean the sink thoroughly. Hot water should not be used or poured in the sink for 24 hours prior to *kashering*. It is recommended that the hot shut-off valve under the sink be turned off 24 hours before *kashering*. The sink should be dry before *kashering*. *Kashering* is accomplished by pouring boiling hot water from a Pesach kettle/pot over every part of the stainless steel sink.

TIP: If a roasting pan is filled and heated, the pouring surface is much wider than a kettle spout. It is not sufficient to pour water on one spot and let it run down the sink. The poured water must touch every part of the sink, including the drain and the spout of the water faucet. It is likely that the *kashering* kettle will need to be refilled a few times before *kashering* can be completed. After *kashering*, the sink should be rinsed with cold water. If hot water was accidentally used in the sink during the 24-hour dormant period, and there is not enough time before Pesach to leave the sink dormant for an additional 24 hours, a *shaila* should be asked.

China Sinks

These sinks cannot be *kashered* and should be cleaned, not used for 24 hours, and completely lined with contact paper or foil. The dishes that are to be washed should not be placed directly into the sink. They must be washed in a Pesach dish pan which sits on a Pesach rack. It is necessary to have separate dish pans and racks for *milchig* and *fleishig* dishes.

Porcelain, Corian or Granite Composite Sinks

These sinks should also be considered similar to a china sink, since there is a controversy as to whether these materials can be *kashered*. Granite composite is a material fashioned from granite and plastic. Many sinks that look like granite are actually granite composite.

Countertops

Silestone, Porcelain Enamel, Corian, Quartz, Plastic/Formica and Granite Composite countertops cannot be *kashered*; they should be cleaned and covered. To place hot food and utensils on these countertops, cardboard or thick pads must be used to cover the counter. **Corian** is also a form of plastic that cannot be *kashered*. Since the chometz penetrates only a thin layer of the counter, it can be sanded down to take off a layer of Corian (the thickness of a piece of paper) and is considered *Kosher l'Pesach*. However, only a qualified contractor should attempt this procedure.

Pure Granite (not granite composite), Marble, Stainless Steel, or Metal may be *kasher*d through *iruy roschin*. **Wood** may also be *kasher*d through *iruy roschin* if it has a smooth surface.

*Iruy rochs*in is accomplished by pouring boiling hot water over every part of the clean countertop. Actual water is needed to *kasher*, not steam. A steam machine may be used if it boils water and sprays it onto the countertops. However, if the steamer only produces steam and not actual boiling water, it can not be used to *kasher*, even if the steam is hotter than 212°F. STAR-K has tested many models of steamers available commercially and has found that almost all of them will only produce hot steam and not boiling water. One method of *iruy rochs*in is to spray or pour a small amount of hot water on the counter and then use a hot iron or heated cast iron plate on top of the water which will [re-]boil it on contact. However, this is dangerous and should only be performed by competent individuals.

Kashering Glass Drinkware

In pre-war Europe, where glass was expensive and hard to obtain, it was customary to *kasher* drinking glasses by immersing them in cold water for three periods of 24 hours. This is accomplished by submerging the glasses for one 24 hour period. The water should then be emptied, refilled and allowed to sit for another 24 hours. The procedure should be repeated a third time, for a total of 72 hours. This method of submerging cannot be used for Pyrex or glass that was used directly on the fire or in the oven. **Arcoroc** and **Corelle** should be treated similar to glass for *kashering* purposes.

In general, *kashering* glasses is recommended only in cases of difficulty. Wherever glasses are readily available for purchase, special glasses for Pesach are preferable.

For other items or questions, feel free to call or email the STAR-K Institute of Halacha at 410.484.4110 or halacha@star-k.org.

See also Cleaning/Kashering Checklist at on page 34.

HOW TO CLEAN/KASHER KITCHEN ITEMS FOR PESACH CHECKLIST

See also "Preparing/Kashering the Pesach Kitchen" on page 25

The following is a checklist reviewing items commonly found in the kitchen and how to prepare them for Pesach.

UTENSIL	PREPARATION
Baby Bottle	Since it comes into contact with chometz (e.g., washed with dishes, boiled in chometz pot), new ones should be purchased.
Baby High Chair	Clean thoroughly. Preferable to cover the tray with contact paper.
Blech	Should be replaced.
Blender/Food Processor	New or <i>Pesachdig</i> receptacle required (plus any part of unit that makes direct contact with food). Thoroughly clean appliance. The blade should be treated like any knife and should be <i>kashered</i> through <i>hagola</i> .
Can Opener	Difficult to clean properly. Should be put away with chometz dishes.
Candlesticks/Tray	Clean thoroughly. Should not be put under hot water in a <i>Kosher l'Pesach</i> sink.
Coffeemakers	Metal coffeemakers that have brewed only unflavored pure coffee. Clean thoroughly. Replace with new or <i>Pesachdig</i> glass carafe and new filters. Metal coffeemakers that have brewed flavored coffee should be cleaned thoroughly. Do not use for 24 hours. Pour one cup of water into chamber. Water should be heated in unit and allowed to drip over the exposed metal base. Replace with new plastic filter holder, new filters, and a new or <i>Pesachdig</i> glass carafe. Plastic coffeemakers should not be <i>kashered</i> .
Colanders	Metal: <i>Libun kal</i> . Plastic: Do not use.
Dentures, Bite Plates, Braces	Clean thoroughly after one has finished eating chometz.
Dishwashers	Cannot be <i>kashered</i>
Electric Burner Drip Pans	Clean thoroughly
Grater	Metal: <i>Libun kal</i> . Plastic: Do not use.
Ice Cream Scooper	<i>Hagola</i>
Ice Cube Trays	See Refrigerator, Freezer

UTENSIL

PREPARATION

Instant Hot Devices	Instant hot devices and individual hot/cold water filters that are connected to the sink with a separate spigot should be <i>kashered</i> along with the sink. Instant hot devices should be turned on during <i>kashering</i> of the instant hot spigot.
Keurig	A Keurig used year-round for only coffee (reg., decaf, and/or flavored – even without a <i>hechsher</i>) can be <i>kashered</i> for Pesach in the following manner: Clean the Keurig machine well and then replace the cup holder (many but not all, Keurig machines have a replaceable K-cup holder). After the clean-out, do not use the machine for 24 hours. After this time has elapsed, run a cycle of hot water to <i>kasher</i> the upper metal pin. If the machine processed a non-kosher product (e.g., chicken soup), it cannot be <i>kashered</i> for year-round use. If it processed real chometz products (e.g., , oatmeal), it cannot be <i>kashered</i> for Pesach.
Light Box	Clean thoroughly
Metal Wine Goblets	<i>Hagola</i>
Metal Wine Trays	<i>Hagola</i>
Mixer	Do not use, even with new blades and bowls.
Pump Pot	If in contact with chometz (e.g., sponge) do not use; otherwise, it does not need <i>kashering</i> .
Refrigerator, Freezer	Thoroughly clean. Lining shelves is not necessary. Ice cube trays (that are filled with water in the sink) should be put away with chometz dishes. Ice cube bins which catch the ice made in the freezer should be thoroughly cleaned and used as usual.
Rings, Finger	<i>Iruy roschin</i>
Rings, Napkin	<i>Hagola</i>
Sensi-Temp Burner	To <i>kasher</i> a Sensi-Temp burner for Pesach, remove the burner from the range top by lifting it up halfway to vertical and pulling it out. Clean it well and wait 24 hours. Once that time has elapsed, pour boiling water over the sensor, which is located in the middle of the burner. Insert the burner back into its socket by reversing the extraction steps. Turn the burner on to its maximum setting until it glows (about 2 minutes).
Smoothie Machine	See Blender
Tables	A table upon which chometz is eaten during the year may be used on Pesach if it is covered with a waterproof covering (e.g., sheet of plastic). It is preferable to put either cardboard or a few layers of paper on the table under the plastic covering. Tablepads may be overturned and used.

UTENSIL	PREPARATION
Towels, Tablecloths, etc.	Those used during the year with chometz may be used during Pesach if they have been laundered with soap and hot water, even if the stains do not come out. The same applies to potholders, bibs, and aprons. Synthetic material, such as Rayon and Terylene that can only withstand a warm water cycle may be used during Pesach after they have gone through a washing with detergent, and only if there are no visible stains after they have been cleaned. Transparent tablecloths may be coated with a powder and should be rinsed off before use. Regarding other tablecloths, see Pesach Product Directory.
Vases	Those used on the table during the year may be used during Pesach if they are washed, both inside and out.
Washing cup (used in kitchen)	Metal: <i>Hagola</i> Plastic: Put away with chometz dishes.
Water Pitchers	Should be put away with chometz dishes.
Water Filters, Metal	A metal water filter that has been on consistently since the previous Pesach may be left on during the <i>kashering</i> of the spigot. If it was first attached sometime after Pesach, it should be removed and the spigot and filter should be <i>kashered</i> separately. The filter may then be reattached and used during Pesach.
Water Filters, Plastic	A plastic water filter that is connected to the faucet should be removed and thoroughly cleaned, including the outside and the coupling. The spigot should be <i>kashered</i> with the filter removed. The filter may then be reattached and used during Pesach.
Water Coolers	Cold water coolers should be cleaned thoroughly. The hot spigot on a water cooler should not be used if it came into contact with chometz during the year.

KITCHEN ITEMS THAT CANNOT BE KASHERED

Bread Machine	George Foreman Grill	Pasta Maker	Silverstone
Ceramic	Immersion Blenders	Plastic Utensils	Stoneware
China	Knives with Plastic Handles	Plastic Vegetable Steamer	Synthetic Rubber
Corningware	Melmac	Porcelain (Enamel) Utensils	Teflon
Crockpot	Mixer	Pyrex	Toaster/Toaster Oven
Dishwasher	Panini Maker	Sandwich Maker	Waffle Iron

See also "Preparing/Kashering the Pesach Kitchen" on page 25.

KASHERING FOR PESACH ACCORDING TO SEPHARDI MINHAGIM

Rabbi Emanuel Goldfeiz, Rav Hamachsir STAR-S

מקצת הלכות הגעלת והכשרת הכלים לפסח לפי מנהגי ספרדים

1. Utensils that are used during the year with *chometz* are forbidden to be used during Pesach without *kashering* them according to Halacha. From the time it is prohibited to eat *chometz* on Erev Pesach, it is forbidden to use the utensils without *kashering* them according to Halacha. The proper *kashering* method used to rid a vessel of *chometz* is dependent upon the original method of food preparation through which *chometz* was absorbed into the vessel.¹
2. We do not recite a *bracha* when *kashering* an item since it is a negative commandment not to consume the taste of non-kosher food.²
3. Sephardic custom is that the method of *kashering* depends upon the most common usage of the vessel. Therefore, it is sufficient to pour boiling hot water from a כלי ראשון on a hot plate after cleaning it to make sure there is no *chometz* on it.³
4. Utensils (such as cups) that were used year-round with cold *chometz*, even if they are made from earthenware or nylon, can be *kashered* by washing them well with cold water.⁴ Although the vessel may have come into contact with hot bread, as long as it was not used within the past 24 hours with hot *chometz*, it can be *kashered*.
5. Utensils made from wood, stone, bone, plastic or nylon can be *kashered* like metal vessels according to the method of their usage.⁵
6. Glassware needs to be washed well inside and out with cold water. Pyrex can be *kashered* in the same manner.⁶
7. A hot water urn needs to be *kashered* for Pesach, even though it was most often used for water and not *chometz*.⁷
8. The *halachot* of *kashering* are numerous and complex. Therefore, it is proper for a *talmid chochom* to oversee the process.⁸

1. שולחן ערוך סימן תנא.

2. איסור והיתר (כלל נח סימן קד) ספר הפרדס (דף כח ע"א) ולא כתוס' עבודה זרה (סז)

3. שולחן ערוך סימן תנא סעיף כה, שו"ת רב פעלים חלק ג (סימן כח), חזון עובדיה פסח עמוד קלד.

4. לא הלכו בכל כלי אלא אחר רוב תשמישו. שו"ת הרשב"א חלק א סימן שעב. ש"ע סימן תנא.

5. חזון עובדיה פסח עמוד קנא, ציץ אליעזר חלק ד סימן ו.

6. שולחן ערוך סימן תנא סעיף כו, אבות דר' נתן פרק מא הלכה ו.

7. מה שאמרו שהולכים בכל כלי אחר רוב תשמישו, אין הכוונה אם השתמשו בו ברוב פעמים לחמץ או לא, אלא לאופן השימוש בכלי. ילקוט יוסף איסור והיתר כרך ג עמוד תסט.

8. ספר חסידים סימן תשל"א.